

BLUE47	Access blue functions					
g-shift						
f-shift	SNAP	STOPW	INFO	TEST	CNST	
unshifted	→I	VIEW	USER □			
Page 2	F1	F2	F3	F4	F5	F6

Prev menu https://47calc.com/doc/R47/Menus/R47v0_Menu_BLUE47_page_1.pdf

Next menu https://47calc.com/doc/R47/Menus/R47v0_Menu_BLUE47_page_3.pdf

Level	Label	Type	FullName	Extended description	Category	Flag	Catalog	Default
Menu p2	BLUE47	MENU	Access blue functions	Access all functions of the DM42-layout g-shift keyboard (blue) and a few of the f-shift keyboard ; Info : Assigned to calculator function SETUP (f[0]) in layout DM42	Keyboard		BLUE47	
F1	→I	Function (monadic, cyclic)	To integer	Convert to Long integer (0), Short integer (8.02-8.16) (cyclic, max 1000 digits) ; Info : Short integer indicated by subscript ₁₀ ; can show TI: 0vrfl<0; or 0vrfl>64 bits : which can be abbreviated as 0F, indicating overflow condition	Integers		→I	
F2	VIEW	Command	View	View register or variable (with preceding TI) ; TAM : VIEW __ Tam menu ; Info : if $\frac{\square}{\square}$ ACT is SET, VIEW will print when executed from the keyboard in MAN, NORM or TRACE ; in Program Entry Mode, $\frac{\square}{\square}$ EN must be SET as well ; if $\frac{\square}{\square}$ ACT is CLEAR and $\frac{\square}{\square}$ EN is SET, VIEW halts execution (R/S)	Status		VIEW	
F3	USER $\square$	Setting	USER mode	Switch on USER mode ; not programmable - in PEM, use flag USER ; Info : To assign USER to a key or button, use ASN (g[DRG]) and spell the name as 'USER' ; during assignment, pressing USER (f[DRG]) opens MyMenu ; Ref : https://47calc.com/doc/R47/Reference/R47v0_Assignment.pdf ; SBI : $\frac{\square}{\square}$	Customisation	USER		OFF
F4								
F5								
F6								
fF1	SNAP	Command	Screenshot	Save screenshot to backup file (.bmp) and save contents of stack or alpha buffer as backup file (.REGS.TSV) in FAT ; plays clicking sound ; Shortcut : [<f>] + [CHS] (DMCP-shortcut for screenshot bitmap only) ; longpress [EXIT] ; NIM long [EXIT] ; PEM longer [EXIT] ; Info : screenshot is saved in file SCREENS/<YYYYMMDD-HHMMSS00>.bmp ; SNAP also appends data to file DATA/<YYYYMMDD-HHMMSS00>.REGS.TSV ; new datafile after timeout of 2 minutes	Input-Output		SNAP	
fF2	STOPW	App	Stopwatch	Stopwatch with running time, counter and countdown (playing BEEP after running down) ; SBI : $\frac{\square}{\square}$	Time functions	RUNTIM	STOPW	
fF3	INFO	MENU	Information	System information and some information about the value in the X-register	Information		INFO	
fF4	TEST	MENU	Testing	Testing functions	Programming		TEST	
fF5	CNST	MENU (ASM)	Constants	Important scientific and technical constants ; Info : In Program Entry Mode, constants selected from the menu are stored in programs as "# ", the reference number, the label and the abbreviated name ; in the equation editor the label is simply preceded by "#" ; Type characters 1-2 to search ; TI : <constant abbreviation> = <value> ; Ref : https://47calc.com/doc/R47/Reference/R47v0_Constants.pdf	Catalog		CNST	
fF6								
gF1								
gF2								
gF3								
gF4								
gF5								
gF6								

p2	BLUE47	Link
F1	→I	
F2	VIEW	
F3	USER □	
F4		
F5		
F6		
fF1	SNAP	
fF2	STOPW	
fF3	INFO	https://47calc.com/doc/R47/Menus/R47v0_Menu_INFO_page_1.pdf
fF4	TEST	https://47calc.com/doc/R47/Menus/R47v0_Menu_TEST_page_1.pdf
fF5	CNST	https://47calc.com/doc/R47/Menus/R47v0_Menu_CNST_page_1.pdf
fF6		
gF1		
gF2		
gF3		
gF4		
gF5		
gF6		